



USSD Short Code	Description of Service
125	Own Number query
123	Balance query
127	Get Tariff Detail
*62*VMSNUMBER#	To activate transfer of all calls to VMS
##002#	Disable all call transfer
*43#	Enable call notice
#43#	Disable call notice
*#43#	Info call notice
##002#	Disable all CFWD
**67*NUMERODEVIAZIONE#	Enable CFWD call and video call if busy
**67*NUMERODEVIAZIONE*11#	Enable CFWD call if busy
**67*NUMERODEVIAZIONE*24#	Enable CFWD video call if busy
##67#	Disable CFWD call and video call if busy
##67**11#	Disable CFWD call if busy
##67**24#	Disable CFWD video call if busy
*#67#	info CFWD is Busy
<b>COMANDI PER DEVIAZIONE SE NON RISPOSTO</b>	
**61*NUMERODEVIAZIONE#	Enable CFWD call and video call if not answered
**61*NUMERODEVIAZIONE*11#	Enable CFWD call if not answered
**61*NUMERODEVIAZIONE*24#	Enable CFWD video call if not answered
##61#	Disable CFWD call and video call if not answered
##61**11#	Disable CFWD call if not answered
##61**24#	Disable CFWD video call if not answered
*#61#	info CFWD if not answered
<b>COMANDI PER DEVIAZIONE SE IL TELEFONO NON E' RAGGIUNBILIE</b>	
**61*NUMERODEVIAZIONE#	Enable CFWD call and video call if unreachable
**61*NUMERODEVIAZIONE*11#	Enable CFWD call if not answered
**61*NUMERODEVIAZIONE*24#	Enable CFWD video call if unreachable
##61#	Disable CFWD call and video call if unreachable



##61**11#	Disable CFWD call if unreachable
##61**24#	Disable CFWD video call if unreachable
*#61#	info CFWD if unreachable
COMANDI PER DEVIAZIONE PER TUTTE LE CHIAMATE IN ARRIVO	
**21*NUMERODEVIAZIONE#	Enable CFWD call and video call unconditional
**21*NUMERODEVIAZIONE*11#	Enable CFWD call unconditional
**21*NUMERODEVIAZIONE*24#	Enable CFWD video call unconditional
##21#	Disable CFWD call and video call unconditional
##21**11#	Disable CFWD call unconditional
##21**24#	Disable CFWD video call unconditional
*#21#	info CFWD unconditional